

Installing SMAP Programs

Minimum System Requirements


- ✓ Windows 64 bit operating system
- ✓ Intel Pentium 4 or AMD processors
- ✓ 8 GB Ram with 30 GB free space in Drive C
- ✓ SVGA monitor

Installation Procedure


1. Uninstall if there are pre-existing SMAP programs.
To uninstall SMAP programs, remove following program using Add/Remove in Control Panel:
 SMAP
Delete following files if they are existing:
 C:\Program Files\Smap
 C:\Windows\Setup1.exe
Rename or delete following folders if they are existing:
 C:\SMAP
 C:\SmapKey
2. Download SMAP-CD.exe from the Download section of www.ComtecResearch.com
3. Run SMAP-CD.exe
SMAP-CD folder at drive C will be created.

2 Installing SMAP Programs


4. Double-click **Setup.exe**




5. Click **OK**




6. Click **Next**
It will take few minutes.
Wait until next step.




7. Click **Continue**



8. Click **OK**



9. Click **OK**



10. Double Click

C:\SmappKey\KeyCheck.exe

Note:

Following two log files will be generated once finished:

C:\SmapSetupAdd.dat

C:\SmapSetupLog.dat

If Smap Installation is successful, delete these two files.

If Smap Installation is not successful,
follow the instruction in SmapSetupAdd.dat.

If you still have problems with Smap Installation,
send these two files to info@ComtecResearch.com

For TUNA and TUNA Plus,
Minimum System Requirement is Windows 32 bit.